

Application of the example from the manual "**MK14 MicroComputer Training Manual**" page 100

Original

YOU-CAN-SEE-S-OF-C-IF-A-JOLLY-FINE-BUY-

```
:180F2000C40D35C40031C40F36C47332C460C8F0C40701C280C9808F8A
:180F380001C4FF027094F3B8DF9CEDC6FF94E590DD8079796D4037774C
:180F500039403E3F6E406D77406E3E7F4079373071406E38383F1F4049
:130F680077406D30403940713F406D4079796D4037773946
:00000001FF
```

nano-SCMP

```
0F20: C4 0D 35 C4 31 C4 0F 36 C4 73 32 C4 60 C8 F0 C4
0F30: 07 01 C2 80 C9 80 8F 01 C4 FF 02 70 94 F3 B8 DF
0F40: 9C ED C6 FF 94 E5 90 DD 80 73 37 39 6D 40 5C 54
0F50: 77 54 40 73 37 39 6D 40 5C 54 77 54 40 73 37 39
0F60: 6D 40 5C 54 77 54 40 73 37 39 6D 40 5C 54 77 54
0F70: 40 73 37 39 6D 40 5C 54 77 54 40 00 00 00 00 00
```

```
:100F2000C40D35C431C40F36C47332C460C8F0C4B4
:100F30000701C280C9808F01C4FF027094F3B8DF3B
:100F40009CEDC6FF94E590DD807337396D405C54AD
:100F50007754407337396D405C5477544073373958
:100F60006D405C547754407337396D405C5477540E
:100F7000407337396D405C547754400000000000E6
:00000001FF
```

CLONES-PHWEB-ME

```
0F20: C4 0D 35 C4 31 C4 0F 36 C4 73 32 C4 60 C8 F0 C4
0F30: 07 01 C2 80 C9 80 8F 01 C4 FF 02 70 94 F3 B8 DF
0F40: 9C ED C6 FF 94 E5 90 DD 80 79 37 40 7c 79 1d 74
0F50: 73 40 6d 79 54 5c 38 39 00 79 37 40 7c 79 1d 74
0F60: 73 40 6d 79 54 5c 38 39 00 79 37 40 7c 79 1d 74
0F70: 73 40 6d 79 54 5c 38 39 00 00 00 00 00 00 00 00
```

```
:100F2000C40D35C431C40F36C47332C460C8F0C4B4
:100F30000701C280C9808F01C4FF027094F3B8DF3B
:100F40009CEDC6FF94E590DD807937407c791d7477
:100F500073406d79545c3839007937407c791d7461
:100F600073406d79545c3839007937407c791d7451
:100F700073406d79545c38390000000000000000B7
:00000001FF
```