



PX41CX interface



HP41 source program

ARAROM.txt

001	LBL 'ARAROM' ; Key: 11	C0 00 F7 01 41 52 41 52 4F 4D
002	FIX 0	9C 00
003	'NOMBRE ? '	F9 4E 4F 4D 42 52 45 20 3F 20
004	PROMPT	8E
005	CLA	87
006	LBL 01	02
007	E3	1B 13
008	X>Y?	45
009	GTO 00	B1 00
010	-	41
011	>'M'	F2 7F 4D
012	GTO 01	B2 00
013	LBL 00	01
014	CLX	77
015	900	19 10 10
016	X<=Y?	46
017	>'CM'	F3 7F 43 4D
018	X>Y?	45
019	CLX	77
020	-	41
021	500	15 10 10
022	X<=Y?	46
023	>'D'	F2 7F 44
024	X>Y?	45
025	CLX	77
026	-	41
027	400	14 10 10
028	X<=Y?	46
029	>'CD'	F3 7F 43 44
030	X>Y?	45
031	CLX	77
032	-	41
033	LBL 02	03
034	E2	1B 12
035	X>Y?	45
036	GTO 00	B1 00
037	-	41
038	>'C'	F2 7F 43
039	GTO 02	B3 00
040	LBL 00	01
041	CLX	77
042	90	19 10
043	X<=Y?	46
044	>'XC'	F3 7F 58 43
045	X>Y?	45
046	CLX	77
047	-	41
048	50	15 10
049	X<=Y?	46
050	>'L'	F2 7F 4C
051	X>Y?	45
052	CLX	77
053	-	41

054	40	14 10
055	X<=Y?	46
056	>'XL'	F3 7F 58 4C
057	X>Y?	45
058	CLX	77
059	-	41
060	LBL 03	04
061	10	11 10
062	X>Y?	45
063	GTO 00	B1 00
064	-	41
065	>'X'	F2 7F 58
066	GTO 03	B4 00
067	LBL 00	01
068	DSE X	97 73
069	X<=Y?	46
070	>'IX'	F3 7F 49 58
071	X>Y?	45
072	CLX	77
073	-	41
074	5	15
075	X<=Y?	46
076	>'V'	F2 7F 56
077	X>Y?	45
078	CLX	77
079	-	41
080	4	14
081	X<=Y?	46
082	>'IV'	F3 7F 49 56
083	X>Y?	45
084	CLX	77
085	-	41
086	LBL 04	05
087	1	11
088	X>Y?	45
089	GTO 00	B1 00
090	-	41
091	>'I'	F2 7F 49
092	GTO 04	B5 00
093	LBL 00	01
094	AVIEW	7E
095	STOP	84
096	END	C0 00 0D



PX41CX interface



Program : ARAROM

Row 1 (Lines 1-3)



Row 2 (Lines 3-7)



Row 3 (Lines 7-15)



Row 4 (Lines 15-21)



Row 5 (Lines 21-29)



Row 6 (Lines 29-38)



Row 7 (Lines 38-44)



Row 8 (Lines 44-54)



Row 9 (Lines 54-62)



Row 10 (Lines 63-70)



Row 11 (Lines 70-78)



Row 12 (Lines 79-88)



Row 13 (Lines 89-96)



Row 14 (Lines 96-96)



End of Bar Code - Total of 14 Rows